Installation Guide



for Windows98, Me, 2000, XP, VISTA, Windows7/8/10 Please note Windows NT can not be used.

IMPORTANT	_
<u> </u>	
USB dongle and its drivers must be properly installed in order for MALT to run.	
For XP users, you must have administration privileges.	
For VISTA/Windows7, see enclosed Note for installing MALT on VISTA or Windows7/8/10.	

CAUTION: DO NOT insert dongle to USB slot until procedure 6

Installation Procedure

- 1. Please find a CD and a USB dongle.
- 2. Confirm that no program is running on your Windows.
- 3. **Mount** the CD-ROM **without inserting** USB dongle and Installation program runs automatically.
 - Should it not run automatically, simply run MaltInst.exe within file explorer. At this time, be sure that the dongle is NOT set in the USB slot.
- 4. Follow the instructions displayed.

Note

- * You can modify MALT install directory in the course.
- * The response of the program may be a bit slow especially when CPU of the PC is old and slow. Please proceed step by step without haste.
- 5. When finished Installation process, you will find MALT icon on your Desktop.
- 6. Before doing any other actions, **insert** the dongle into available USB slot. Windows OS will detect the dongle as a new hardware, and install the driver automatically.
- 7. Double click the MALT icon to execute the MALT.

Should it not run properly, for example, error code 600,601 or 602 persist, then please try either of the followings.

- A: Restart the Windows, and Double click the MALT icon again.
- B: Uninstall MALT by the Installation program, and install again while the dongle is left as it is set in USB slot.

If the installation failed with a message "MALT already exists" and Uninstallation also failed, then delete C:\(\text{\text{\$W\$}}\) indows\(\text{\text{\$Y\$}}\) malt.ini and reinstall.

* Please DO NOT LOSE the dongle. We do not re-issue the dongle unless it has been returned to us as defected one.

Kagaku Gijutsu-Sha Attention: Takafumi Matsumoto 2-10-8 Yanagibashi, Taito-ku, Tokyo 111-0052 JAPAN Tel 81-3-5809-1132 Fax 81-3-5809-1138 e-mail: malt@kagaku.com http://www.kagaku.com/malt